


Preparing the USB Memory Stick (Minimum 1GB Capacity)

Please ensure that the memory stick is blank and insert it into an available USB port on your PC.

The stick should be blank and should be formatted to NTFS.

- Locate the USB drive in File Explorer
- Right-click on it
- Select Format
- Choose NTFS from the drop-down menu.
- Click Format




Downloading the software

Please download the software from this link: [ZRDG_240815REDS.exe](#)


Once downloaded please double-click on the file to open it.

- When prompted please browse to the USB memory Stick Location.



- Click on "Extract".


You USB should look like this when finished



When completed you can remove the USB stick from your PC

Installing the software

1. Turn off the Cabinet.
2. Insert the USB memory Key into one of the available USB Ports



3. Power up the cabinet.
4. System Launcher will run.
5. The Shell Update will be verified, installed, and then copied.
6. The Shell will run.
7. The Game will run.
8. Once the game has loaded press the Test Button to enter the test menu
9. Press the Test Button again to enter the System Information Page
10. Check Shell is: 240815REDS and Game is: 240815REDS.